



### You will need:

- 36 x Paisley duo beads (PD)
- 5 x 6mm round beads
- 4 x 7mm / 8mm 2-hole cabochons
- 9 x 4mm Firepolish crystals
- 9 x size 8/0 seed beads
- 1g x size 11/0 seed beads
- 2g x size 15/0 seed beads
- Small piece of purl
- Fastening of your choice
- Needle and matching thread or Fireline



**NOTE** The bracelet shrinks once you start adding rows 2 and on so you will need it a bit longer to begin with

If you need to lengthen or shorten by a little then do so at the fastening

If unsure of length, you could make 8 units and then add the 9<sup>th</sup> if necessary

### To start

- Thread your needle with a wingspan of thread – this should be enough to complete the bracelet – you will be using this singly

### First Unit

- Passing your needle through hole at the fat part of the PD, with the point of the bead facing away from the tail thread, pick up PD – 1 x 15/0 – PD – 1 x 11/0 – 1 x 4mm – 1 x 11/0
- Now pass your needle through another PD, this time with the point of the bead facing the tail thread, then pick up 1 x 15/0 and pass your needle through a 4th PD
- Pick up 5 x 15/0 and pass your needle back through the 2nd hole of the 4th PD
- Pass your needle through the 3rd PD and pick up 1 x 8/0
- Pass your needle through the 2nd holes of the 2nd and 1st PD and pick up 5 x 15/0
- Now pass your needle through all the beads as before until you reach the 4th PD and then pass your needle through the first 15/0 of the 5 that you added along the outside of that PD
- Pull the beads gently together so there is as little thread showing as possible



Second unit

- Passing your needle through hole at the fat part of the PD, with the point of the bead facing away from the tail thread, pick up PD – 1 x 15/O – PD – 1 x 11/O – 1 x 4mm – 1 x 11/O
- Now pass your needle through another PD, this time with the point of the bead facing the tail thread, then pick up 1 x 15/O and pass your needle through a 4th PD
- Pick up 5 x 15/O and pass your needle back through the 2nd hole of the 4th PD
- Pass your needle through the 3rd PD and pick up 1 x 8/O
- Pass your needle through the 2nd holes of the 2nd and 1st PD and pick up 4 x 15/O



- Pass your needle through the 15/O where you first started and you will find that this unit sits the other way up to the previous one
- Now pass your needle through all the beads as before until you reach the 4th PD of this unit and then pass your needle through the first 15/O of the 5 that you added along the outside of that PD
- Pull the beads gently together so there is as little thread showing as possible

Third and following units

- Repeat as per the second unit until the bracelet wraps around your wrist – remember it will shrink as you add the next rows
- If in doubt, make the bracelet smaller and you can always add an extra unit on before adding the final fastening
- When you have completed the final unit, end with your thread coming out of the 5th or the 15/Os on the outside of the last PD



Row 2

- Pick up 1 x 11/O – 1 x 6mm – 1 x 11/O
- Pass your needle through the 9 x 15/Os along the outer edges of the next 2 x PDs
- Pick up 1 x 15/O and pass your needle through one hole of the cabochon (the hole which will allow the cabochon to sit closest to the PDs in this unit)
- Then pick up 1 x 15/O and pass your needle through the next 9 x 15/Os
- You will now be in position to add the 1 x 11/O – 1 x 6mm – 1 x 11/O before passing your needle through the next 9 x 15/O



- Continue along the row, adding the 11/Os & 6mm to one side of the bracelet and the 15/Os and 8mm cabochon to the other
- When you have added the last 11/O – 6mm – 11/O, pass your needle through the 5 x 15/O and you are in position to add the first part of the fastening



#### Adding the fastening

- Pick up 5 x 15/O – 1 x 11/O – small piece of purl and first part of fastening
- Pass your needle back through the 11/O and pull the purl gently to form a loop enclosing the fastening
- Pick up 5 x 15/O and pass your needle through the 15/O in between the 1<sup>st</sup> and 2<sup>nd</sup> PDs from this end

#### Row 3

- Work your needle through the 2<sup>nd</sup> PD – 11/O – 4mm – 11/O – 3<sup>rd</sup> PD – 15/O
- Pick up 6 x 15/O & 1 x 11/O
- Pass your needle through the 2<sup>nd</sup> hole of the cabochon
- Pick up 1 x 11/O & 6 x 15/O and pass your needle into the 15/O between the 1<sup>st</sup> & 2<sup>nd</sup> PDs of the next unit on this side
- Repeat all the way along the row and once you have added the last set of beads, pass your needle through all the beads until it is coming out of the 1<sup>st</sup> 6mm on the other side of the bracelet



#### Row 4

- Pass your needle through the 11/O after the 6mm and pick up 7 x 15/O
- Pass your needle through the 15/O in between the 1<sup>st</sup> & 2<sup>nd</sup> PDs of the next unit
- Continue passing your needle through the 2<sup>nd</sup> PD – 11/O – 4mm – 11/O – 3<sup>rd</sup> PD – 15/O
- Pick up 7 x 15/O and pass your needle through the next 11/O – 6mm – 11/O
- When you reach the last 6mm, pass your needle through the 11/O after it and then the 5 x 15/O and you are in position to add the 2<sup>nd</sup> part of the fastening in the same way as you did the first

